




THE TELOS ALLIANCE®

Create. Communicate. Connect.

Decoding Dolby E with AudioSuite in Pro Tools 2018.7-2018.12 (Bug Resolved in PT 2019.5)

1. Create a 48kHz/24 bit Pro Tools session.








THE TELOS ALLIANCE®

Create. Communicate. Connect.

2. Import your Dolby E-encoded file onto a stereo audio track in the timeline.



3. Create eight mono audio tracks. These will be left empty.





1241 Superior Avenue Cleveland, OH 44114 USA | +1.216.241.7225 | TelosAlliance.com



THE TELOS ALLIANCE®

Create. Communicate. Connect.

4. Create a 7.1 audio track and place it at the top of the nine tracks that you created in steps 1-3.



Telos®

Omnia®

25
SEVEN

AXIA®

M
MINNETONKA

L LINEAR ACOUSTIC®



1241 Superior Avenue Cleveland, OH 44114 USA | +1.216.241.7225 | TelosAlliance.com



THE TELOS ALLIANCE®

Create. Communicate. Connect.

5. Select the encoded audio track and the 8 blank mono audio tracks in the timeline simultaneously (with Command Focus enabled, you can select your encoded audio and then use “Shift + ;” to select the tracks below).





1241 Superior Avenue Cleveland, OH 44114 USA | +1.216.241.7225 | TelosAlliance.com



THE TELOS ALLIANCE®

Create. Communicate. Connect.

6. Drag these tracks onto the 7.1 audio track you created in step 4.



Telos®

Omnia®

25 SEVEN

AXIA®

M MINNETONKA

L4 LINEAR ACOUSTIC®


1241 Superior Avenue Cleveland, OH 44114 USA | +1.216.241.7225 | TelosAlliance.com



THE TELOS ALLIANCE®

Create. Communicate. Connect.

7. You will now be able to decode the audio to the interleaved 7.1 track you created in step 4.




1241 Superior Avenue Cleveland, OH 44114 USA | +1.216.241.7225 | TelosAlliance.com



THE TELOS ALLIANCE®

Create. Communicate. Connect.



If you have any questions, please do not hesitate to contact us at techsupport@telosalliance.com.

Happy decoding!



1241 Superior Avenue Cleveland, OH 44114 USA | +1.216.241.7225 | TelosAlliance.com