

Cepheo Quality and Sample Management

Release note

October 2025

Version 21.0




Table of Contents

1	Copyright Notice	8
1.	CEPHEO Build 10.0.20190625.1	9
1.1.	General	9
1.2.	Changed	9
1.3.	Known Issues.....	9
2.	CEPHEO Build 10.0.20191108.1	10
2.1.	General	10
2.2.	Changed	10
2.3.	Known Issues.....	10
3.	CEPHEO Build 10.0.20191121.1	11
3.1.	General	11
3.2.	Changed	11
3.3.	Known Issues.....	11
4.	CEPHEO Build 10.0.20191220.1	12
4.1.	General	12
4.2.	Changed	12
4.3.	Known Issues.....	12
5.	CEPHEO Build 10.0.20200129.1	13
5.1.	General	13
5.2.	Changed	13
5.3.	Known Issues.....	13
6.	CEPHEO Build 10.0.20200205.1	14
6.1.	General	14
6.2.	Changed	14
6.3.	Known Issues.....	14
7.	CEPHEO Build 10.0.20200226.1	15
7.1.	General	15
7.2.	Changed	15
7.3.	New	15
7.4.	Known Issues.....	16
8.	CEPHEO Build 10.0.20200507.1	17
8.1.	General	17
8.2.	New	17
8.3.	Known Issues.....	17
9.	CEPHEO Build 10.0.202005.1	18
9.1.	General	18
9.2.	New	18

9.3. Known Issues	18
10. CEPHEO Build 10.0.20200619.1	19
10.1. General	19
10.2. Changed	19
10.3. New	19
10.4. Known Issues	20
11. CEPHEO Build 10.0.20201022.1	21
11.1. General	21
11.2. Changed	21
11.3. New	21
11.4. Known Issues	22
12. CEPHEO Build 10.0.20201126.1	23
12.1. General	23
12.2. Changed	23
12.3. New	23
12.4. Known Issues	24
13. CEPHEO Build 10.0.20201126.1	25
13.1. General	25
13.2. New	25
13.3. Known Issues	25
14. CEPHEO Build 10.0.20210112.1	26
14.1. General	26
14.2. New	26
14.3. Known Issues	27
15. CEPHEO Build 10.0.20210204.1	28
15.1. General	28
15.2. New	28
15.3. Known Issues	28
16. CEPHEO Build 10.0.20210622.1	29
16.1. General	29
16.2. New	29
16.3. Changed	30
16.4. Changed	30
16.5. Changed	30
16.6. Changed	30
16.7. Changed	30
16.8. Known Issues	31
17. CEPHEO Build 10.0.20210817.1	32
17.1. General	32

17.2. New	32
17.3. Known Issues	32
18. CEPHEO Build 10.0.20210825.1	33
18.1. General	33
18.2. New	33
18.3. Known Issues	33
19. CEPHEO Build 10.0.20211014.1	34
19.1. General	34
19.2. Changed	34
19.3. Changed	34
19.4. Fixed	35
20. CEPHEO Build 10.0.20211116.1	36
20.1. General	36
20.2. Changed	36
21. CEPHEO Build 10.0.20211125.1	37
21.1. General	37
21.2. New	37
21.3. New	37
21.4. New	38
22. CEPHEO Build 10.0.20220110.1	39
22.1. General	39
22.2. New	39
22.3. Changed	39
22.4. Fixed	40
23. CEPHEO Build 10.0.20220330.1	41
23.1. General	41
23.2. New	41
23.3. New/changed	41
23.4. New/changed	42
24. CEPHEO Build 10.0.20220330.1	43
24.1. General	43
24.2. Changed	43
25. CEPHEO Build 10.0.20220524.1	44
25.1. General	44
25.2. Changed	44
25.3. Fixed	44
26. CEPHEO Build 10.0.20220824.1	46
26.1. General	46
26.2. Fixed	46

27. CEPHEO Build 10.0.20220920.1	47
27.1. General	47
27.2. Fixed	47
28. CEPHEO Build 10.0.20221020.1	48
28.1. General	48
28.2. Fixed	48
29. CEPHEO Build 10.0.20221102.1	49
29.1. General	49
29.2. Changed	49
29.3. New	49
30. CEPHEO Build 10.0.20221111.1	50
30.1. General	50
30.2. Changed	50
31. CEPHEO Build 10.0.20230224.1	51
31.1. General	51
31.2. New	51
32. CEPHEO Build 10.0.20230622.3	52
32.1. General	52
32.2. Changed	52
33. CEPHEO Build 10.0.20230814.1	53
33.1. General	53
33.2. Changed	53
34. CEPHEO Build 10.0.20231011.1	54
34.1. General	54
34.2. New	54
34.3. New	54
35. CEPHEO Build 10.0.20231115.1	55
35.1. General	55
35.2. Fixed	55
36. CEPHEO Build 10.0.20240117.1	56
36.1. General	56
36.2. Changed	56
36.3. Fixed	56
36.4. Known Issues	56
37. CEPHEO Build 10.0.20240312.3	57
37.1. General	57
37.2. New	57
37.3. New	57
37.4. New	58

37.5. New	58
37.6. New	58
37.7. New	58
37.8. New	58
38. CEPHEO Build 10.0.20240809.1	59
38.1. General	59
38.2. New	59
38.3. New	59
39. CEPHEO Build 10.0.20240829.1	60
39.1. General	60
39.2. New	60
39.3. Change	60
40. CEPHEO Build 10.0.20241002.1	61
40.1. General	61
40.2. New	61
40.3. New	61
40.4. New	62
40.5. Fixed	62
40.6. Fixed	62
41. CEPHEO Build 10.0.20241026.1	63
41.1. General	63
41.2. Fixed	63
41.3. New	63
41.4. Fixed	63
42. CEPHEO Build 10.0.20241113.1	64
42.1. General	64
42.2. Fixed	64
43. CEPHEO Build 10.0.20250125.1	65
43.1. General	65
43.2. New	65
43.3. Fixed	65
43.4. Fixed	65
44. CEPHEO Build 10.0.20250221.1	67
44.1. General	67
44.2. Fixed	67
44.3. Fixed	67
45. CEPHEO Build 10.0.20250329.1	68
45.1. General	68
45.2. Fixed	68

45.3. New	68
46. CEPHEO Build 10.0.20250429.1	69
46.1. General	69
46.2. Fixed	69
46.3. Fixed	69
46.4. Fixed	69
47. CEPHEO Build 10.0.20250612.2	70
47.1. General	70
47.2. Fixed	70
47.3. Fixed	70
47.4. Fixed	70
47.5. Fixed	71
48. CEPHEO Build 10.0.20250619.1	72
48.1. General	72
48.2. Fixed	72
49. CEPHEO Build 10.0.20250715.1	73
49.1. General	73
1.1 Fixed	73
49.2. New	73
50. CEPHEO Build 10.0.20250909.1	75
50.1. General	75
50.2. Fixed	75
50.3. Known Issues.....	76

1 COPYRIGHT NOTICE

Copyright © Cepheo 2025 All rights reserved

This publication may not be copied, in whole or in part, without Cepheo's consent.

Cepheo, the Cepheo logo, and all Cepheo brand names and product names in this document are either trademarks or registered trademarks of Cepheo.

All other trademarks belong to their respective owners.

Microsoft Dynamics is a trademark of Microsoft Corporation in the United States of America and/or other countries.

The information in this document is confidential and may be legally privileged. It is intended solely for the recipient and access to this document by anyone else is unauthorized. If you are not the intended recipient, any disclosure, copying, distribution or any action taken, or omitted to be taken, in reliance on it is prohibited and may be unlawful. When addressed to our clients, any opinions or advice contained in this document are subject to the terms and conditions expressed in the governing client contract.

1. CEPHEO BUILD 10.0.20190625.1

1.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20190625.1	June 25 - 2019

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.3	-	What's new or changed in Finance and Operations apps version 10.0.5 (October 2019)
Platform	Platform Update 27	-	What's new or changed in Platform update 29 for Finance and Operations apps (October 2019)

1.2. Changed

Functionality	Description
Purchase item-receive failed when using the PI Item receive	Due to changes in the class that controls the warehousing process for 'Purchase item receive' the PI process that would display any auto created samples/advanced quality orders wasn't working anymore and a temporary workaround has been to set parameter 'Use advanced control in warehouse item receiving' to NO, this issue has been resolved in this release and the functionality re-established:



1.3. Known Issues

Number	Name	Description
n/a		

2. CEPHEO BUILD 10.0.20191108.1

2.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20191108.1	November 10 - 2019

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.5	-	What's new or changed in Finance and Operations apps version 10.0.5 (October 2019)
Platform	Platform Update 29	7.0.5372	What's new or changed in Platform update 29 for Finance and Operations apps (October 2019)

2.2. Changed

Functionality	Description
Extend AQO/Sample creation sequencing (37808)	The sequencing framework triggering creation of Advanced quality orders and/or Samples in a frequency based on batch, batch + product or product has been enhanced and will respect the settings in the advanced quality associations.
Extend advanced Quality order batch validation unregistered sample check (37942)	When using the value 'Batch' in the parameter 'Update disposition dimension' (release on batch level) together with the 'Auto validate priority one lines' and 'Auto validate advanced quality orders' parameters set to yes, there is a check against samples related to the batch (with status 'Created' i.e. NOT yet registered) to prevent updating the disposition code on the batch if 'open' (un-registered samples) still exist for the batch number, this check has been changed to batch + item for the sample.

2.3. Known Issues

Number	Name	Description
n/a		

3. CEPHEO BUILD 10.0.20191121.1

3.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20191121.1	November 22 - 2019

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.5	-	What's new or changed in Finance and Operations apps version 10.0.5 (October 2019)
Platform	Platform Update 29	7.0.5372	What's new or changed in Platform update 29 for Finance and Operations apps (October 2019)

3.2. Changed

Functionality	Description
QSM: Manual reservation fails, as it doesn't find available inventory (38210)	Due to a change in field naming, the manual reservation on sales orders failed with information of insufficient inventory when activating all 4 dimensions in 'Detailed availability by dimension'. This has been fixed.

3.3. Known Issues

Number	Name	Description
n/a		

4. CEPHEO BUILD 10.0.20191220.1

4.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20191220.1	December 20th - 2019

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.7	-	What's new and changed in Dynamics 365 Finance version 10.0.7 (January 2020)
Platform	Platform Update 31	7.0.5457	What's new or changed in Platform update 31 for Finance and Operations apps (January 2020)

4.2. Changed

Functionality	Description
QSM: Extend electronic signature for manual update of AQO statuses (38823)	Included in the module are 4 bespoke Signature requirements. The requirement for triggering electronic signature when Priority one status is updated or the Status of the entire Adv. quality order, this was no longer triggering individual database log records. This has been fixed.

4.3. Known Issues

Number	Name	Description
n/a		

5. CEPHEO BUILD 10.0.20200129.1

5.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20200129.1	January 30th - 2020

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.7	-	What's new and changed in Dynamics 365 Finance version 10.0.7 (January 2020)
Platform	Platform Update 31	7.0.5457.35479	What's new or changed in Platform update 31 for Finance and Operations apps (January 2020)

5.2. Changed

Functionality	Description
QSM: Quality Samples entity cannot save InventDim relations (39829)	The 2 entities: Quality sample (EGLQSMProdLabSampleRegTableEntity) and Sample sample types (EGLQSMSampleSampleTypesTableEntity) have been updated to save not only the storage/tracking dimension sets (origin and storage) but also the InventDim ID's.

5.3. Known Issues

Number	Name	Description
n/a		

6. CEPHEO BUILD 10.0.20200205.1

6.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20200205.1	February 6, 2020

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.7	-	What's new and changed in Dynamics 365 Finance version 10.0.7 (January 2020)
Platform	Platform Update 31	7.0.5457.35479	What's new or changed in Platform update 31 for Finance and Operations apps (January 2020)

6.2. Changed

Functionality	Description
QSM: Expected completion time with Lab section cutoff (40001)	When a product has been set up to generate an advanced quality order when a sample is registered in lab, and one or more tests hold a value in 'Lab sections' and this lab section incl. a 'Cut off' time i.e. a time by which the registering the sample in lab must be done to be able to start the analysis today, this time will be respected in collaboration with the calendar attached to the lab section as well.

6.3. Known Issues

Number	Name	Description
n/a		

7. CEPHEO BUILD 10.0.20200226.1

7.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample
Management Version

Release Date

10.0.20200226.1

February 28, 2020

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.7	-	What's new and changed in Dynamics 365 Finance version 10.0.7 (January 2020)
Platform	Platform Update 31	7.0.5457.35479	What's new or changed in Platform update 31 for Finance and Operations apps (January 2020)

7.2. Changed

Functionality

Description

n/a

7.3. New

Functionality

Description

QSM: Add test measure values to quality order line overview grid in Advanced quality orders form (40502)

On the forms 'Advanced quality order' and 'Register test results' the field group 'Test measurement values' have been added as display fields in the Overview grid and are showing the values according to decimals on the UoM for the (fraction) tests, this is to give a better overview of the values on the overview tab page.
The fields are (on adv. quality orders) editable on the Test tab page.

Sequence	Test	Description	Results error	Mean error	Standard error	UoM	Decimals	Test value	Standard	Min	Max	Min tolerance	Max tolerance (%)	Test result
18	Fraction 1.0	Fraction 1.0	✓	✓	✓	0	0 decimal	44.8	44.8	0.0	100.0	100.00	0.00	0.00
20	Fraction 2 decimals	Fraction 2 decimals	✓	✓	✓	2	2 decimals	85.80	85.80	0.00	100.00	100.00	0.00	0.00
22	Fraction 3 decimals	Fraction 3 decimals	✓	✓	✓	3	3 decimals	98.246	98.246	0.000	100.000	100.000	0.000	0.000
40	Fraction 4 decimals	Fraction 4 decimals	✓	✓	✓	4	4 decimals	92.7405	92.7405	0.0000	100.0000	100.0000	0.0000	0.0000

7.4. Known Issues

Number	Name	Description
n/a		

8. CEPHEO BUILD 10.0.20200507.1

8.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20200507.1	May 7, 2020

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.7	-	What's new and changed in Dynamics 365 Finance version 10.0.7 (January 2020)
Platform	Platform Update 31	7.0.5457.35488	What's new or changed in Platform update 31 for Finance and Operations apps (January 2020)

8.2. New

Functionality	Description
QSM: Create entity for test results table (41977)	To facilitate test results for Advanced quality order lines coming in via a power app. A new data entity for test result lines has been added: EGLAQCIInventQualityOrderLineResultsEntity The new entity has also been programmed to carry out the updates of phase and status on the Advanced quality order line when test results are being imported via the entity.

8.3. Known Issues

Functionality	Description
n/a	

9. CEPHEO BUILD 10.0.202005.1

9.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20200520.1	May 29, 2020

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.7	-	What's new and changed in Dynamics 365 Finance version 10.0.7 (January 2020)
Platform	Platform Update 31	7.0.5457.35488	What's new or changed in Platform update 31 for Finance and Operations apps (January 2020)

9.2. New

Functionality	Description
AQC: Correction of Batch expiry date (42089)	Some businesses within the Process Industry area have very cautious approach to the 'Expiration date' of their products and do therefore have a policy of backdating/rounding the calculated Expiration date to another date e.g. the last day of the month of the prior month, for this purpose a new setup parameter has been added to the Tracking number group form that allows you to use a calendar with open and closed days to calculate a new Expiration date either backwards in time or forward.

9.3. Known Issues

Functionality	Description
n/a	

10. CEPHEO BUILD 10.0.20200619.1

10.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20200619.1	June 19, 2020

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.7	-	What's new and changed in Dynamics 365 Finance version 10.0.7 (January 2020)
Platform	Platform Update 31	7.0.5457.35488	What's new or changed in Platform update 31 for Finance and Operations apps (January 2020)

10.2. Changed

Functionality	Description
n/a	

10.3. New

Functionality	Description
AQC: Extension of Test Group line sequence functionality (42325)	<p>On the test group lines we have a functionality for determining how often the current test should be included in an Advanced quality order.</p> <p>With this update the setup options have been extended to enable a setup based not only on a counter/per days but also stated per <i>Sequence type</i>. The Sequence type options are Batch, Product and Batch/product.</p> <p>The functionality applies for all advanced quality orders triggered by the system (not manually created) and of course triggered from a sample being registered in lab.</p> <p>In the same update we have also enhanced the error message you get upon copy of a test group if the Id exceeds 10 characters.</p>

10.4. Known Issues

Functionality	Description
n/a	

11. CEPHEO BUILD 10.0.20201022.1

11.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20201022.1	October 23, 2020

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.7	-	What's new and changed in Dynamics 365 Finance version 10.0.7 (January 2020)
Platform	Platform Update 31	7.0.5457.35488	What's new or changed in Platform update 31 for Finance and Operations apps (January 2020)

11.2. Changed

Functionality	Description
QSM(AQC): Change behavior of quality order line result entry in the "Register tests results" form. (45359)	In the form 'Register test results' when test results were entered in the field 'Value' on the header section it would only accept (.) as comma separator, this has been changed to accept test results based on the users setting of 'Date, time, and number format' (as it is the case on lines)
QSM(AQC): Error in receipt process (44181)	When using the receipt process with a mobile device menu item with parameter 'Generate license plate' marked YES together with requirements for vendor registration via the Item model group an error (<i>The value 'InventBatchID is not found in the map</i>) was thrown – This has been fixed.

11.3. New

Functionality	Description
AQC: Quality work for transfer orders (44181)	With this release we have added the reference type 'Transfer orders' to advanced quality association thus making it possible to trigger adv. Quality orders and/or Quality samples upon receipt of Transfer orders at the 2 events: Registration or Product receipt and also have the created quality elements presented in the receipt process

Functionality	Description
	via the Warehousing app.
	<p>The parameter 'Use advanced quality control in warehouse item receiving' has been moved from being a general parameter to being set up on the individual additional menu items that now are supported (see below).</p> <p>Furthermore, we have made it possible to use the following receipt processes where the create quality elements are presented during the (receipt) work creation processes:</p> <ul style="list-style-type: none"> Purchase order line receiving (current) Purchase order line receiving and put away (NEW) Purchase order item receiving (current) Purchase order item receiving and put away (NEW) Transfer order line receiving (NEW) Transfer order line receiving and put away (NEW) Transfer order item receiving (NEW) Transfer order item receiving and put away (NEW) License plate receiving (NEW) License plate receiving and put away (NEW) Mixed license plate receiving (NEW) – Source: Transfer, Purchase orders, LP receive, Return order receiving Mixed license plate receiving and put away (NEW) – Source: Transfer, Purchase orders, LP receiving, Return order receiving

11.4. Known Issues

Functionality	Description
n/a	

12. CEPHEO BUILD 10.0.20201126.1

12.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20201126.1	November 30 th 2020

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.7	-	What's new and changed in Dynamics 365 Finance version 10.0.7 (January 2020)
Platform	Platform Update 31	7.0.5457.35488	What's new or changed in Platform update 31 for Finance and Operations apps (January 2020)

12.2. Changed

Functionality	Description
QSM(AQC): Move WHS reservation code to extension, and enable batch reservation without LP (45397)	WHS reservations considering the Process Industry elements such as batch disposition code down to license plate level was up to now kept in a separate copy of the WHS reservations classes. This functionality has been moved to an extension instead.

12.3. New

Functionality	Description
QSM(AQC): Move WHS reservation code to extension, and enable batch reservation without LP (45397)	Furthermore a set of new parameters can allow on hand on a location that is <i>not</i> license plate enabled to be available for reservation is needed: New general parameter on the 'Advanced quality control parameters': 'Activate batch reservation for on hand without LP, where allowed' (default NO) can if set to YES enable a new parameter on the Location profiles 'Allow batch reservation without LP' to allow batch reservations to consider on hand

Functionality	Description
QSM(QSM): Allow AQO treatment time calculations using lab sections for all quality order reference types (45836)	qty's with no LP's for reservation (if the batch disposition code allows the issue). Up till now, when calculating the Expected start date and expected Completions dates, the settings on the Lab section (calendar and cut off time) have only been considered when the quality order was of reference type= Quality sample. We have extended this functionality to apply for all reference types. Note: Quality orders of reference type 'Quality samples' uses the 'Arrived in lab' as start time + date for the calculation whereas the other reference types use the start of the calendar day, either the general parameter calendar or the one from the lab section if present.

12.4. Known Issues

Functionality	Description
n/a	

13. CEPHEO BUILD 10.0.20201126.1

13.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20201126.1	December 17, 2020

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.7	-	What's new and changed in Dynamics 365 Finance version 10.0.7 (January 2020)
Platform	Platform Update 31	7.0.5457.35488	What's new or changed in Platform update 31 for Finance and Operations apps (January 2020)

13.2. New

Functionality	Description
Add InventTransfer type to sample reference types on Adv. test associations (46198)	When Transfer order reference type was implemented in last update, the option to select the sample reference type= Transfer order on Adv. Quality order associations for type 'Quality samples' was not made available, this has been added with this update.
"Create sample"-form reference lookup for transfer orders (46231) + Add Itemid filtering to transfer order lookup in create samples form (46257)	When creating a sample of reference type = Transfer order in the 'Create sample' form, the transfer orders available for selection in the 'Reference number' field will be only transfer orders that contains the item number chosen.

13.3. Known Issues

Functionality	Description
n/a	

14. CEPHEO BUILD 10.0.20210112.1

14.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20210112.1	January 20 th 2021

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.7	-	What's new and changed in Dynamics 365 Finance version 10.0.7 (January 2020)
Platform	Platform Update 31	7.0.5457.35488	What's new or changed in Platform update 31 for Finance and Operations apps (January 2020)

14.2. New

Functionality	Description
Registration of test result and samples as part of WHS RAF and production startup flows (45247)	<p>When working with warehouse processes for a production/batch order, using the warehouse app, the possibility for presentation and registration of quality samples, and/or advanced quality orders, created from advanced quality associations triggered by the Production processes is now possible.</p> <p>The functionality is now also available for Production processes: A new parameter 'Use quality control processes' has been introduced on the device menu items when using the following activity codes/work creation process:</p> <ul style="list-style-type: none"> - Start production - Report as finished - Report as finished and put away

14.3. Known Issues

Functionality	Description
n/a	

15. CEPHEO BUILD 10.0.20210204.1

15.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20210204.1	February 10, 2021

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.7	-	What's new and changed in Dynamics 365 Finance version 10.0.7 (January 2020)
Platform	Platform Update 31	7.0.5457.35488	What's new or changed in Platform update 31 for Finance and Operations apps (January 2020)

15.2. New

Functionality	Description
QSM: Allow sample creation, in the WHS app, without license plate ID (46593)	When creating a sample using the Warehousing app., it has up till now been mandatory with the following data entry: Item number, batch number, license plate ID and reference number (for the reference type). To make it possible to create samples where no license plate has been issued yet or for stock located in a non-license plate-controlled location it is now possible to allow creation without entering a license plate, this is achieved by a new parameter 'Skip inventory validation' that has been added to the Mobile device menu items when using the indirect activity code 'Create sample'.

15.3. Known Issues

Functionality	Description
n/a	

16. CEPHEO BUILD 10.0.20210622.1

16.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20210622.1	June 22, 2021

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.16	-	What's new and changed in Dynamics 365 Finance version 10.0.16
Platform	Platform Update 40	7.0.5860.35679	What's new or changed in Platform update 40 for Finance and Operations apps

16.2. New

Functionality	Description
QSM: Quality workspace: New dashboard for quality work (47098)	<p>A new workspace called 'Quality analyses has been added to the available workspaces. The workspace can be accessed under Workspaces or via a new menu item in the Quality module.</p> <p>The workspace provides an overview of quality data based on Test, test groups, items, batches, Advanced quality orders and quality samples. The workspace contains 3 tab-pages: Summary, Advanced quality orders/test results and Quality samples hold several charts/graphs with various filtering options to display quality data in many combinations. This dashboard can provide a speedy daily (or weekly, monthly etc.) overview of the Quality control part of the operation.</p>

16.3. Changed

Functionality	Description
QSM: Menu item "View test results" missing on "InventTestGroup" form (48491)	The menu item 'View test results' that will show the recorded test results for an Adv. Quality orders of reference type = Quality samples, has been added to the form 'Test groups' and will show all test results for selected batch(es) updated using the current test group.

16.4. Changed

Functionality	Description
QSM: Jump ref to quality orders from inventItemTracing not working (48492)	On the form Item trace, it is possible to view the quality orders associated with the item + batch you are viewing using the Item trace functionality. This functionality is also available for Adv. Quality orders and now works correctly.

16.5. Changed

Functionality	Description
AQC+QSM: Minor fixes, "Postponed days" does not use time zone correctly (48528)	When using the 'Days postponed' field on a quality order, the calculation of expected start and completion days didn't consider the time zone of the legal entity, this has been changed.

16.6. Changed

Functionality	Description
License Manager updated	The CEPHEO license manager is a tool that enables CEPHEO to create, allocate and control licenses for CEPHEO IP in a smoother way utilizing newer technology such as Power app.

16.7. Changed

Functionality	Description
Moved to new version	When releasing a module, we always make sure to develop on the 'lowest' version that any of our customers currently are on. This is for CEPHEO Quality and Sample

Functionality	Description
	Management version 10.0.16. Note that all releases always are validated against the latest current version as well.

16.8. Known Issues

Functionality	Description
n/a	

17. CEPHEO BUILD 10.0.20210817.1

17.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20210817.1	August 18, 2021

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.16	-	What's new and changed in Dynamics 365 Finance version 10.0.16
Platform	Platform Update 40	7.0.5860.35679	What's new or changed in Platform update 40 for Finance and Operations apps

17.2. New

Functionality	Description
QSM/BMD: Manufacturing date functionality changed to include journals and Warehousing app processes (49644)	The functionality for updating Manufacturing date on batches during production processes has been extended to include all 3 Report as finished processes: From the production order, Via Report as finished journals and Via the Report as finished process in the warehousing app.

17.3. Known Issues

Functionality	Description
n/a	

18. CEPHEO BUILD 10.0.20210825.1

18.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20210825.1	September 7, 2021

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.16	-	What's new and changed in Dynamics 365 Finance version 10.0.16
Platform	Platform Update 40	7.0.5860.35679	What's new or changed in Platform update 40 for Finance and Operations apps

18.2. New

Functionality	Description
QSM: Refactoring of code for index hashing on the Adv. Quality ass. table (49661)	To accommodate a change Microsoft has made to the hashing used on the InventDim (inventory dimensions) index in upcoming version 10.0.21, a change had to be made to the Advanced quality association index. The change has no impact on existing or new data and no changes will be visible.

18.3. Known Issues

Functionality	Description
n/a	

19. CEPHEO BUILD 10.0.20211014.1

19.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20211014.1	October 19, 2021

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.16	-	What's new and changed in Dynamics 365 Finance version 10.0.16
Platform	Platform Update 40	7.0.5860.35679	What's new or changed in Platform update 40 for Finance and Operations apps

19.2. Changed

Functionality	Description
QSM: Modify reservation extension to allow picking items in warehouse while retaining status reserved (50343)	When running the WHS process of "Raw material picking" using work to perform pick and put for a reserved Batch quantity, the wanted status (after pick) for the consumption qty on the production line inventory transaction, can be controlled by the warehouse parameter 'Raw material picking' to be either "Picked" or "Reserved physical". In the current solution the inventory transaction will end up with status "On order" and thereby loose the reservation to the wanted Batch quantity.

19.3. Changed

Functionality	Description
QSM: Enable Sample label print for the "Start production order" activity code in the warehousing app, when Advanced quality-processes are enabled. (50571)	For warehouse menu items using the activity code "Start production order" it must be possible to enable the "Print label" feature when the parameter "Use quality control processes" is enabled. If the "Use quality control processes" is disabled, the "Print label" will be disabled automatically.

Functionality	Description
	When activating the "Print label" parameter, the document routing setup for work order type "Quality control" must be triggered when using the menu item to start a production order and an advanced quality association is setup to create a sample upon this event.

19.4. Fixed

Functionality	Description
QSM: Batch attributes display wrong format/value when test results are entered using the warehouse app. (50454)	<p>In a setup running European language in combination with EN-US settings for 'Date, time, and number format', the reported test values (decimal values) using the warehousing app is registered on the test line without the decimal (12,34 > 1234).</p> <p>Changing the language to EN-US so that the user settings are the same will solve the issue, but it must be possible to have a mix of settings. This has been fixed in this release.</p>

20. CEPHEO BUILD 10.0.20211116.1

20.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20211116.1	November 18, 2021

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.16	-	What's new and changed in Dynamics 365 Finance version 10.0.16
Platform	Platform Update 40	7.0.5860.35679	What's new or changed in Platform update 40 for Finance and Operations apps

20.2. Changed

Functionality	Description
QSM: Quality order report does not contain line details (51024)	The quality order report does output registered test results for each test in the quality order. Due to previously change in the solution the behavior of test results record changed to no longer initiate an empty record at creation of a quality order, the quality order report now again will show tests regardless of test results have been entered or not. If no test results exist for a test, the value and unit are shown as a "-".

21. CEPHEO BUILD 10.0.20211125.1

21.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20211125.1	December 7, 2021

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.16	-	What's new and changed in Dynamics 365 Finance version 10.0.16
Platform	Platform Update 40	7.0.5860.35679	What's new or changed in Platform update 40 for Finance and Operations apps

21.2. New

Functionality	Description
QSM: Streamline rounding of test results for advanced quality orders (51033)	Handling of rounding principles for test results is introduced. To ensure that rounding behavior is not changed automatically from the current solution, 3 new parameter field are introduced on Tests to be inherited to 'Test group lines' and further to 'Advanced quality order lines' (editable in all 3 places). It is only when activated the new rounding behavior is used.

21.3. New

Functionality	Description
QSM: Quality Sample Type data on label (51214)	Up till now the only Samples related fields added to the framework for generating labels have been 'Sample ID' and 'Sample type ID'. With this release 9 further fields have been added to enable these fields to be used on a samples/sample type labels.

21.4. New

Functionality	Description
QSM: Enter warehouse location when creating sample from WHS app (51228)	<p>When using the warehouse app to create a quality sample (Activity code = Create sample) it is now possible to add information of all storage active dimensions, according to the storage dimension group for the item number in question. The dimension "Inventory status" is not going to be included, even if it is set as active.</p> <p>Site and Warehouse information will still be defaulted from the warehouse worker creating the sample, remaining storage dimensions are not mandatory, but optional.</p>

22. CEPHEO BUILD 10.0.20220110.1

22.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20220110.1	January 12, 2022

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.16	-	What's new and changed in Dynamics 365 Finance version 10.0.16
Platform	Platform Update 40	7.0.5860.35679	What's new or changed in Platform update 40 for Finance and Operations apps

22.2. New

Functionality	Description
QSM: New entity for creating advanced quality orders (51523)	A new data entity 'Create advanced quality order V1' has been added to enable creation of Advanced quality orders via Excel import, Power apps or Flows. Additional validation and enhancements have been made to the manual creation of adv. Quality orders in the client because of the addition of the new entity.

22.3. Changed

Functionality	Description
QSM(AQC+QSM): Cannot manually create advanced quality orders of type "Quality sample" as well as "Transfer order" (517793)	In the client it was not possible to manually create an Adv. Quality order with reference type: Quality sample or Transfer order in the Advanced quality order form directly, this is now possible.

22.4. Fixed

Functionality	Description
QSM(AQC+QSM): Error when links from alerts are clicked for advanced quality orders and quality samples (51737)	When alerts had been setup for Adv. Quality orders or Quality samples activating the link resulted in an error. This has been fixed.

23. CEPHEO BUILD 10.0.20220330.1

23.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20220330.1	April 5, 2022

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.16	-	What's new and changed in Dynamics 365 Finance version 10.0.16
Platform	Platform Update 40	7.0.5860.35679	What's new or changed in Platform update 40 for Finance and Operations apps

23.2. New

Functionality	Description
QSM: Remove requirement for entering "Inventory status" when creating adv. quality orders that are NOT updating inventory status (52555)	<p>Changes: The requirement for an Invent status to be entered on creation has been retained, if the test group updates inventory status.</p> <p>It will now only be allowed to set a value to update inventory status, if the inventory status dimension is filled out (coming from setup on e.g., Site or warehouse)</p> <p>The requirements for inventory status dimension to be filled out, for creation of quality orders that do not update inventory status has been removed.</p>

23.3. New/changed

Functionality	Description
QSM: Change batch expiry date validation to occur only when the batch expiry date is being changed (53011)	When using the functionality of updating the Expiration date when production/batch orders are reported as finished (setup on the Tracking dimension group of the released product) in combination with the parameter setting on a formula version 'Lot inheritance' where the batch dates and/or -attributes are inherited from the ingoing products to

Functionality	Description
	the finished products, there was a need for more outcomes to determine the behavior of the dates being updated. Now there are 3 options: The calculated expiration date is validated according to the setup (error if date falls on a closed day), The validation is skipped and calculated (inherited) date stands or Inherited dates are corrected according to the setup.

23.4. New/changed

Functionality	Description
QSM: QSM: Batch disposition time not set when selecting multiple batches in query (53029)	<p>Changes: When updating batch disposition status codes, using the standard job 'Update batch disposition status' and applying a code that would set disposition time, it would only update the time one record.</p> <p>A new periodic job 'Advanced update batch disposition status' replaces the job when update of disposition time is used in the current company. The 'Reset batch disposition status' job on the form Batches works as it has until now.</p>

24. CEPHEO BUILD 10.0.20220330.1

24.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20220429.1	May 3, 2022

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.16	-	What's new and changed in Dynamics 365 Finance version 10.0.16
Platform	Platform Update 40	7.0.5860.35679	What's new or changed in Platform update 40 for Finance and Operations apps

24.2. Changed

Functionality	Description
QSM: Exclude LP disposition code check from reservations on a not WHS-enabled warehouse (53392)	Using the standard functionality warehouse enabled products that are to be consumed on a batch/production order should be moved to a non-LP controlled location (that is marked YES in parameter 'Allow batch reservation without license plate' on the profile) and where the batch holds a batch disposition code that is available for production reservation, is then available for picking. If you are not using the standard functionality and are instead moving the warehouse enabled product's on hand to a non-warehouse enabled warehouse's location, the on hand loses its license plate and Inventory status values, this resulted in the on hand not being viewed as available stock, this has not been changed.

25. CEPHEO BUILD 10.0.20220524.1

25.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20220524.1	May 30, 2022

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.16	-	What's new and changed in Dynamics 365 Finance version 10.0.16
Platform	Platform Update 40	7.0.5860.35679	What's new or changed in Platform update 40 for Finance and Operations apps

25.2. Changed

Functionality	Description
QSM: Change disposition codes of multiple license plates (53718)	When updating the LP disposition code manually from the form License plates (Reset disposition status) there was a limit to the number of records the container could hold. The functionality has now been changed so that you can select the number of records you need and update these. We have added a new parameter that enables you to run the change <i>without</i> updating the record (default setting), this generates a list of the records that <i>would</i> be updated, only if you tick YES in the parameter 'Run with update' will the selected records be updated. The function 'Reset disposition time' has also been changed to work in the same way.

25.3. Fixed

Functionality	Description
QSM: Batch attributes are not updated after validation of Advanced Quality Order (53748)	If a quality order result line wasn't included in the result, part of the standard code resulted in the flowing lines batch attribute values not being transferred. This has been changed so that all lines marked YES in field 'Update inventory batch attribute' have the batch attribute values

Functionality	Description
	transferred to the corresponding attributes on the batch in question.

26. CEPHEO BUILD 10.0.20220824.1

26.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20220824.1	August 30, 2022

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.24	-	What's new and changed in Dynamics 365 Finance version 10.0.24
Platform	Platform Update 48	7.0.6253.76	What's new or changed in Platform update 48 for Finance and Operations apps

26.2. Fixed

Functionality	Description
QSM: Display wrong value in view test results due to changing test value (CEPHEO Quality and Sample Management) (54476)	If the user settings have different values between language and Number formats e.g., En-US language and a European number format (where comma (,) is normally used as separator) is rounding shown in field Test value on the General tab page on the Advanced quality order lines, this field was used to display test results in the View test results form that subsequently also was shown incorrectly, this has been fixed.

27. CEPHEO BUILD 10.0.20220920.1

27.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20220920.1	September 21, 2022

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.24	-	What's new and changed in Dynamics 365 Finance version 10.0.24
Platform	Platform Update 48	7.0.6253.76	What's new or changed in Platform update 48 for Finance and Operations apps

27.2. Fixed

Functionality	Description
QSM: Enable the "Add to workspace"-button in the Quality samples form (55203)	On the form 'Quality samples' the standard button 'Add to workspace' wasn't enabled, this has been fixed.

28. CEPHEO BUILD 10.0.20221020.1

28.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20221020.1	October 26 th 2022

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.30	-	What's new and changed in Dynamics 365 Finance version 10.0.30
Platform	Platform Update 54	7.0.6592.33	What's new or changed in Platform update 54 for Finance and Operations apps

28.2. Fixed

Functionality	Description
QSM: Create new QSM infrastructure for 10.0.30 due to obsoleted method on the class 'WHSWorkExecuteDisplay' (55422)	<p>With version 30 a method on one of the classes used in warehouse management receipt processes was made obsolete and changes has been made to the processes that used the old method. Additionally, all workspaces have been changed in layout by Microsoft from horizontal to vertical, the 'Quality analysis' workspace is now also using the new layout template.</p> <p>When using the indirect activity code 'Start production' any created adv. Quality work was no longer displayed, this was due to the above-mentioned change and has been fixed.</p>

29. CEPHEO BUILD 10.0.20221102.1

29.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20221102.1	November 7th, 2022

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.30	-	What's new and changed in Dynamics 365 Finance version 10.0.30
Platform	Platform Update 54	7.0.6592.33	What's new or changed in Platform update 54 for Finance and Operations apps

29.2. Changed

Functionality	Description
QSM: Change the behaviour of "Advanced update batch disposition status" to not report an error if no records found, when run in batch (55684)	The job "Advanced update batch disposition status" has been changed to write to infolog instead of issuing an error, when no records found and running in batch.

29.3. New

Functionality	Description
QSM: Find advanced quality orders on batch orders using data/filter from 'samples' (55709)	<p>A new menuitem "Advanced quality orders from samples" has been added to the production orders form and listpage.</p> <p>Using the menuitem will open the advanced quality orders form showing all advanced quality orders originating from samples taken from the current production/batch order.</p>

30. CEPHEO BUILD 10.0.20221111.1

30.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20221111.1	November 14th, 2022

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.30	-	What's new and changed in Dynamics 365 Finance version 10.0.30
Platform	Platform Update 54	7.0.6592.33	What's new or changed in Platform update 54 for Finance and Operations apps

30.2. Changed

Functionality	Description
QSM: Quality control processes in combination with license plate receiving and put away (55821)	When using the LP receive and put away process in combination with being presented with created quality work (orders/samples) the receipt location is not defaulted to the guide until you press key 'Suggest location', this has been changed.

31. CEPHEO BUILD 10.0.20230224.1

31.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality and Sample Management Version	Release Date
10.0.20230424.1	April 27, 2023

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.30	-	What's new or changed in <u>Finance</u> and <u>Operations</u> apps version 10.0.30
Platform	Platform Update 54	7.0.6592.134	What's new or changed in Platform update 54 for Finance and <u>Operations</u> apps

31.2. New

Functionality	Description
QSM: Rebranding solution to Cepheo (57833)	The module QSM is being released with the module rebranded to Cepheo, in connection with this a new version of License manager is also delivered.

32. CEPHEO BUILD 10.0.20230622.3

32.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality and Sample Management Version	Release Date
---	--------------

10.0.20230622.3	June 26, 2023
------------------------	---------------

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.30	-	What's new or changed in <u>Finance</u> and <u>Operations</u> apps version 10.0.30
Platform	Platform Update 54	7.0.6592.134	What's new or changed in Platform update 54 for Finance and <u>Operations</u> apps

32.2. Changed

Functionality	Description
QSM: LP disposition DateTime can be updated unintentionally when an LP record is updated (58610)	When using batch disposition codes that are setup to use Disposition time, the value of this field can in some cases unintentionally be updated when an LP record is updated, this has been changed.

33. CEPHEO BUILD 10.0.20230814.1

33.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality and Sample Management Version	Release Date
10.0.20230814.1	August 15, 2023

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.30	-	What's new or changed in <u>Finance</u> and <u>Operations</u> apps version 10.0.30
Platform	Platform Update 54	7.0.6592.134	What's new or changed in Platform update 54 for Finance and <u>Operations</u> apps

33.2. Changed

Functionality	Description
QSM: Error on manual 'Change LP disposition code with disposition time' (58826)	An error was shown when trying to update disposition code manually via the periodic job or in the License plate form if the filter options had been removed, this has been changed so that these fields can't be removed (are no longer visible in the range options).

34. CEPHEO BUILD 10.0.20231011.1

34.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality and Sample Management Version	Release Date
10.0.20231011.1	October 11, 2023

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.33	-	What's new or changed in Finance and Operations apps version 10.0.33
Platform	Platform Update 57	7.0.6861.30	What's new or changed in Platform update 57 for Finance and Operations apps

34.2. New

Functionality	Description
QSM: Add fields to entities as requested by Cegeka. (59387)	<p>3 data entities have been updated with the following fields:</p> <ol style="list-style-type: none"> 1. EcoResReleasedProductsV2Entity → EGLAQCWhsLicensePlateDispositionCode + EGLQSMPLPSequencePrinciple 2. WHSLicensePlateEntity → EGLAQCDispositionCode + EGLAQCDispositionDateTime (both read only) 3. WHSWarehouseLocationProfileEntity → EGLAQCAAllowBatchReservationWithoutLP

34.3. New

Functionality	Description
QSM: Direct access to register test results from advanced quality order. (56237)	The form 'Register test results' that can be accessed directly from the Quality menu/Common has been added as a new menu item button on the form 'Advanced quality orders'. The menu item is enabled for orders in state 'Open' and will open the form for the current adv. Quality order.

35. CEPHEO BUILD 10.0.20231115.1

35.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality and Sample Management Version	Release Date
10.0.20231115.1	November 20, 2023

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.33	-	What's new or changed in Finance and Operations apps version 10.0.33
Platform	Platform Update 57	7.0.6861.30	What's new or changed in Platform update 57 for Finance and Operations apps

35.2. Fixed

Functionality	Description
QSM: Test value not updated after entering test result in new window (59768)	When using the results form on the Advanced quality order lines, and opening it in a new window, the entered results were not shown as updated until the window was closed, this has been fixed.

36. CEPHEO BUILD 10.0.20240117.1

36.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality and Sample Management Version	Release Date
10.0.20240117.1	January 19, 2024

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.36	-	What's new or changed in Finance and Operations apps version 10.0.36
Platform	Platform Update 60	7.0.7036.51	What's new or changed in Platform update 60 for Finance and Operations apps

36.2. Changed

Functionality	Description
QSM: Samples with no related quality associations should retain status 'Registered in lab' when status 'Registered in lab' is set. (i.e. NOT moved to status 'To archive') (60093)	If a sample, that was Registered in lab didn't find a record in Adv. Quality associations that would trigger a quality order, it was, system wise, moved directly to archive, this has been changed to remain in status 'Registered in lab' if no quality orders are triggered.

36.3. Fixed

Functionality	Description
QSM: Warehouse specific inventory transactions cannot be activated, and location blocking is not working with warehouse specific inventory transactions (59780)	The activation of certain areas of Warehouse specific inventory transactions were blocked from being activated, due to Quality and Sample management module. This has been fixed.

36.4. Known Issues

Number	Name	Description
n/a		

37. CEPHEO BUILD 10.0.20240312.3

37.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality and Sample Management Version	Release Date
10.0.20240312.3	March 18 th , 2024

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.36	-	What's new or changed in Finance and Operations apps version 10.0.36
Platform	Platform Update 60	7.0.7036.51	What's new or changed in Platform update 60 for Finance and Operations apps

37.2. New

Functionality	Description
QSM: Possibility to postpone quality order finished date with a reason code) (60393)	The Advanced Quality Orders have been extended with a new reason code field related to a new table 'Advanced quality order postponement reason codes', where reason codes for postponing finished dates can be created. The new Reason code field has been added to the Advanced Quality Order form below the "Days postponed" field as a non-mandatory field. The new Reason code field has also been added to the Advanced Quality Order entity 'Advanced quality order headers'.

37.3. New

Functionality	Description
QSM: Monitor timeframe on disposition code (60422)	Field 'Disposition changed' has been added to the batch and license plate field + history tables, to make it possible to use the value of the last update of disposition code on a batch or LP as the one side of a time frame (e.g. Last updated vs now). The field has also been added to the data entities 'WHSLicensePlateEntity' and 'InventItemBatchEntity'.

37.4. New

Functionality	Description
QSM: Mandatory pallet remarks on manually blocked (60426)	To be able to enter a remark if a batch/LP is manually updated to a certain batch disposition code, a new check box field 'Manual remark is mandatory' has been added to the batch disposition master'. If set to yes for a code, and you manually change to this code on a batch/LP, you are prompted to fill in a remark, this remark is cleared again if changed to another code (manually or automatically) but is part of the history data.

37.5. New

Functionality	Description
QSM: Warning when doing registration of test result that will fail (60462)	To prevent that registration of test results that are typed wrongly are performing unintended updates for quality orders, a dialog is being presented if the tested value is outside the expected values. The user now must confirm values that will fail the test.

37.6. New

Functionality	Description
QSM: Quality test master form for an item (60471)	To get an overview of the total test setup for a specific item number, a test master overview form is available. The form can be found from the released product in the quality section.

37.7. New

Functionality	Description
QSM: Warning if a test result has not been entered within a specified timeframe (60472)	The single test will be calculated with information of expected treatment finished time, according to the setup of expected treatment time and the calendar setup for the lab section performing the analyses. If no lab section or no calendar is specified, the base calendar in advanced quality control parameters is used

37.8. New

Functionality	Description
QSM: Item trace form now also show data for Advanced quality orders and Quality samples (60524)	<p>The item tracing form will include information about standard quality data as well as information about advanced quality data. The advanced quality data is shown divided into 3 different types:</p> <ul style="list-style-type: none"> • Advanced quality orders derived from a process • Quality samples derived from a process • Advanced quality orders derived from quality samples

38. CEPHEO BUILD 10.0.20240809.1

38.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality and Sample Management Version	Release Date
10.0.20240809.1	August 13, 2024

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.38	-	What's new or changed in Finance and Operations apps version 10.0.38
Platform	Platform Update 62	7.0.7120.159	What's new or changed in Platform update 62 for Finance and Operations apps

38.2. New

Functionality	Description
(QSM) It must be possible to create a quality setup dependent on sample sources (60746)	When using quality samples in production it is possible to enter at which resource the sample was taken e.g. a tab somewhere in the process. We are extended the setup of Quality associations so allowing stating a resource value (table) on quality associations of ref. type Quality sample with sample ref. type = Production, Co-product production and Route operation to enable resource specific quality orders.

38.3. New

Functionality	Description
(QSM) Automation of transfer of values to batch attributes. (60743)	The transfer of batch attribute values based on multiple test results is possible as a manual process for adv. Quality orders of type 'Quality samples', this process is manual as you decide between possible multiple test results in what will be the representative value for the batch. We have extended the functionality to make the process even easier and more automated (se further in the User guide).

39. CEPHEO BUILD 10.0.20240829.1

39.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality and Sample Management Version	Release Date
10.0.20240829.1	August 29, 2024

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.38	-	What's new or changed in Finance and Operations apps version 10.0.38
Platform	Platform Update 62	7.0.7120.159	What's new or changed in Platform update 62 for Finance and Operations apps

39.2. New

Functionality	Description
(QSM) Block picking at disposition code change on LP sources (61076)	When using a 2-part process for picking a sales order: Pick from location and put to staging → Pick in staging and put to the bay door, the class used in the last pack is the SO load class. In this class the functionality to check against LP disposition code had not been implemented. This means that we now will check again against the LP disposition code in case it has been updated in between being picked in the storage location and 2 nd time in staging to a blocked for picking.

39.3. Change

Functionality	Description
(QSM) Enable AllowRowVersionChangeTracking (60931)	All Cepheo customer tables now have the property "row version change tracking" enabled. This is to enable the tables to be able to be transferred through Synapse Link to a storage account in Azure Data Lake due to another method being deprecated in November 2024. The list of over 200 tables can be found in the changeset 'Product Backlog Item 60931: Enable AllowRowVersionChangeTracking'.

40. CEPHEO BUILD 10.0.20241002.1

40.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality and Sample Management Version	Release Date
10.0.20241002.1	October 2, 2024

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.38	-	What's new or changed in Finance and Operations apps version 10.0.38
Platform	Platform Update 62	7.0.7120.159	What's new or changed in Platform update 62 for Finance and Operations apps

40.2. New

Functionality	Description
QSM- Priority of quality control work depending on a deadline. (60744)	To be able to better plan which adv. Quality orders to prioritize dependent on when the batch will be used for sales, a new tile has been added to the Quality analysis workspace 'Adv. Quality orders in order of delivery' that sorts the opens quality orders in order of delivery date + time on the production/batch orders.

40.3. New

Functionality	Description
QSM- Samples when product is transferred between containers. (60745)	<p>When 2 or more batches must be merged into a new batch number, the standard functionality 'All batch merges' should be used.</p> <p>The result of a batch merge is posted via a BOM journal (the on hand of the existing batches are deducted and the new combined batch that now holds the on hand is received). To be able to trigger quality samples/adv. Quality orders when this action is performed, the standard reference type 'Inventory' is used (holds standard no functionality on the quality framework) is used. Standard all quality orders are an inventory 'movement' (receiving a purchase order, RAF a production order etc.). Taken out a sample from a static on hand qty in the warehouse has not been possible up till now, it had to be linked to a order reference. A menu button to create a quality sample based on the receipt line on the BOM journal has been added and from there an adv. Quality order can be created/triggered (via setup in Adv. Quality associations) or manually).</p>

40.4. New

Functionality	Description
QSM- Automatic creation of Non-Conformance. (60747)	When a test or test result fails on an adv. Quality order line, you can setup the system to trigger additional tests to be added to the current adv. Quality order. This framework has been extended to also be able to automatically trigger a Non-conformance order of the new reference type 'Adv. Quality order' if wanted.

40.5. Fixed

Functionality	Description
(QSM) Enable AllowRowVersionChangeTracking (60931)	Re-checked in for this release after small change.

40.6. Fixed

Functionality	Description
(QSM) EGLAQCEGLAQCI InventTestAssociation TableTests.test_ WrkCtrTableTableRelationValidation Failed in 10.0.20240919.1 (61186)	Automated test case failing due to error in lookup for resources in Adv. Quality associations– This has been fixed.

41. CEPHEO BUILD 10.0.20241026.1

41.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality and Sample Management Version	Release Date
10.0.20241026.1	October 30, 2024

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.38	-	What's new or changed in Finance and Operations apps version 10.0.38
Platform	Platform Update 62	7.0.7120.159	What's new or changed in Platform update 62 for Finance and Operations apps

41.2. Fixed

Functionality	Description
QSM- New tile: Advanced quality orders in order of delivery. Filter does not work properly. (61214)	The new workspace-tile added in the previous release was not (besides the type of Adv. Quality order) showing only Adv. Quality orders of status OPEN, this has been fixed.

41.3. New

Functionality	Description
QSM- Disposition date/time cannot be uploaded with entity License plates (60748)	The field 'Disposition date/time' (updated via the periodic job 'Reset disposition time' on license plates) and other related fields were not editable in the data entity 'WHSLicensePlateEntity' due to fields being updated via jobs in other places. Mapping is now possible, and field values can be updated through import.

41.4. Fixed

Functionality	Description
QSM- Incorrect physical reservation after completing work (61110)	Scenario: The warehouse parameter 'Issue status after raw material picking' is set to value 'Reserved physical', and you have 2 or more production orders hold physical reservations against the same batch + LP, and the 1 st work line pick has been completed, the subsequent productions issue transactions were showing an incorrect value – This has been fixed.

42. CEPHEO BUILD 10.0.20241113.1

42.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality and Sample Management Version	Release Date
10.0.20241113.1	December 12, 2024

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.38	-	What's new or changed in Finance and Operations apps version 10.0.38
Platform	Platform Update 62	7.0.7120.159	What's new or changed in Platform update 62 for Finance and Operations apps

42.2. Fixed

Functionality	Description
QSM- Test master overview is not correctly filtered (60840)	In the form 'Test master overview', that can be accessed from the released products form/tab page Inventory. The data in the form should show all advanced quality associations where the current item is part of either as a table value (the item number) or because it is part of a record setup on quality group level. The form was showing too many records, this has now been fixed.

43. CEPHEO BUILD 10.0.20250125.1

43.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality and Sample Management Version	Release Date
10.0.20250125.1	February 3, 2025

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.38	-	What's new or changed in Finance and Operations apps version 10.0.38
Platform	Platform Update 62	7.0.7120.159	What's new or changed in Platform update 62 for Finance and Operations apps

43.2. New

Functionality	Description
Tile showing advanced quality orders with related Non-Conformance (61311)	A new tile 'Tile showing advanced quality orders with related auto-created 'Non-Conformance orders' of has been added to the Quality analysis workspace to work with Adv. Quality orders, where auto-created Non-conformance orders of type 'Adv. Quality order' has been created. NOTE: NC orders of this type can't as of now be created manually.

43.3. Fixed

Functionality	Description
Cannot move an LP with two items on it (61243)	An error ' <i>The value inventbatchID is not found in the map</i> ' was shown when trying to move a license plate containing 2 or more items that are batch controlled in the warehousing app, this has been fixed.

43.4. Fixed

Functionality	Description
Immediate replenishment is created twice with error on load qty as the consequence (61366)	When setting up an immediate replenishment template on a pick action location directive line, the replenishment work was triggered twice. This has been fixed, but required some code in location directive search to be remodeled. The bespoke classes deleted are: EGLAQCWhsLocationDirective, EGLAQCWhsLocationDirectiveEventHandlers.

Functionality	Description
	If you have extensions on these classes you will need to move the code.

44. CEPHEO BUILD 10.0.20250221.1

44.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality and Sample Management Version	Release Date
10.0.20250221.1	February 26th, 2025

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.38	-	What's new or changed in Finance and Operations apps version 10.0.38
Platform	Platform Update 62	7.0.7120.159	What's new or changed in Platform update 62 for Finance and Operations apps

44.2. Fixed

Functionality	Description
Incorrect physical reservation after completing work - Bug version 2 (61473)	When using the warehouse parameter 'Issue status after raw material picking' with value 'Reserved physical' and either the same batch has on hand in different locations or in the same location, the reservations were not always kept making the issue status revert to 'On order'- This has been fixed.

44.3. Fixed

Functionality	Description
Sales reservation issues LP disposition code (61496)	Qty's shown as available for reservation were not always correct when some of the qty's already were reserved against another sales order when using LP disposition codes and when using locations without LP control, the calculation of available stock has been restructured to show the correct figures.

45. CEPHEO BUILD 10.0.20250329.1

45.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality and Sample Management Version	Release Date
---	--------------

10.0.20250329.1	April 4th, 2025
------------------------	-----------------

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.41	-	What's new or changed in Finance and Operations apps version 10.0.41
Platform	Platform Update 65	7.0.7367.49	What's new or changed in Platform update 65 for Finance and Operations apps

45.2. Fixed

Functionality	Description
Sales reservation issues LP disp code - 2nd case (61525)	Re-writing of the codes used when reservation requests are made for items set up with reservation hierarchy 'BatchAbove'.

45.3. New

Functionality	Description
Change of quality sample status based on advanced quality order status change to passed/failed (61434)	To ease the updating work of samples related to adv. Quality orders that have been fully updated (status changed to Pass or Fail), a new feature has been added that contains a new parameter + a new batch job, that can update quality samples/-sample types, that have triggered quality orders, when the order is updated to status Pass or Fail.

46. CEPHEO BUILD 10.0.20250429.1

46.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality and Sample Management Version	Release Date
10.0.20250429.1	May 7th, 2025

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.41	-	What's new or changed in Finance and Operations apps version 10.0.41
Platform	Platform Update 65	7.0.7367.49	What's new or changed in Platform update 65 for Finance and Operations apps

46.2. Fixed

Functionality	Description
Quality orders receiving on scanner will result in incorrect main screen after QA-trigger (61699)	Fix is implemented for the WMS App. Now both mobile device menu items "Purchase order line receiving" and "Purchase order line receiving and put away" behave the same and keeps the information of the purchase order when the operator moves to the quality processes (take sample / register test results) and back to the line receiving menu.

46.3. Fixed

Functionality	Description
Register test results does not work if column is moved (61719)	Fixed. Before the behavior of the field was affected by the group of fields, it was sitting next to. The value field is no longer locked for input even if the column is moved.

46.4. Fixed

Functionality	Description
Auto-created non conformance orders Problem type must be mandatory (61674)	Fixed this issue by making the problem type field mandatory, if a test has the parameter "automatic creation of non-conformance" toggled to "yes".

47. CEPHEO BUILD 10.0.20250612.2

47.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality and Sample Management Version	Release Date
10.0.20250612.2	June 12th, 2025

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.41	-	What's new or changed in Finance and Operations apps version 10.0.41
Platform	Platform Update 65	7.0.7367.49	What's new or changed in Platform update 65 for Finance and Operations apps

47.2. Fixed

Functionality	Description
No duty / privilege's for Advanced quality order postponement reason codes (61772)	The table "Advanced quality order postponement reason codes" is now added to security privileges. Users can be assigned or denied privileges to be able to access and work in this table.

47.3. Fixed

Functionality	Description
Control frequency of tests based on product alone is not working (61775)	The fix is related to the method of calculating sampling frequency based on the Product method. It was incorrectly behaving as the Batch-product method. Now, only the product registration entry is considered for calculations, regardless of the batch number.

47.4. Fixed

Functionality	Description
Both 'Create advanced quality order' and 'Create sample' are set to No (61805)	A fix has been made to the Advanced quality associations configuration. Previously, it was possible to create a record with both the "Create advanced quality order" and "Create sample" checkboxes set to NO. The update now ensures that at least one of these checkboxes must be set to YES.

47.5. Fixed

Functionality	Description
Return order form can't be opened due to Cepheo (62018)	A fix has been made to the avoid naming collision with recently released Microsoft upgrades related to Return orders.

48. CEPHEO BUILD 10.0.20250619.1

48.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality and Sample Management Version	Release Date
---	--------------

10.0.20250619.1	June 23th, 2025
------------------------	-----------------

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.41	-	What's new or changed in Finance and Operations apps version 10.0.41
Platform	Platform Update 65	7.0.7367.49	What's new or changed in Platform update 65 for Finance and Operations apps

48.2. Fixed

Functionality	Description
'Create advanced quality order' set to No and 'Create sample' set to Yes	Fix for an critical issue, that makes unable to create an advanced quality associations entry when "Create advanced quality order" is not enabled.

49. CEPHEO BUILD 10.0.20250715.1

49.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality and Sample Management Version	Release Date
10.0.20250715.1	July 17, 2025

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.41	-	What's new or changed in Finance and Operations apps version 10.0.41
Platform	Platform Update 65	7.0.7367.49	What's new or changed in Platform update 65 for Finance and Operations apps

1.1 Fixed

Functionality	Description
Stability testing quality work - cannot enter results (61960)	Fixed bug with products with a setup on released product -> quality -> test of stability. If a sample was created but not registered in lab automatically, there was no quantity on the stability testing advanced quality orders. With this fix the quantity is calculated using the setup on the items sampling defined on the test group used by setup on test of stability on the released product.
Duplicate name found in text box of SSRS report EGLQSMQualityOrderReport (61942)	This fix ensures that Lasernet can now successfully connect to and process the EGLQSMQualityOrderReport.Report without errors.

49.2. New

Functionality	Description
Possibility to unarchive an auto archived sample (in status "To archive") (61759)	Improved handling of Advanced Quality Orders process allows auto archived samples to be registered in the lab. Operators can now change the status of auto archived samples to "arrived in lab," enabling them to manually create advanced quality orders by selecting "Registered in Lab" and confirming via a dialog box. This update complements the "Automated archival quality samples" feature.
Blocking Manual Picking of Blocked License Plates (60930)	This new functionality ensures that manual picking of blocked license plates from any location is prevented, whether through the D365 form (create Picking list) or via a mobile device (Register Material Consumption). The

Functionality	Description
	system will display an error message, preventing the action and enhancing inventory management consistency.

50. CEPHEO BUILD 10.0.20250909.1

50.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20250909.1	September 10, 2025

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.41	-	What's new or changed in Finance and Operations apps version 10.0.41
Platform	Platform Update 65	7.0.7367.49	What's new or changed in Platform update 65 for Finance and Operations apps

50.2. Fixed

Functionality	Description
License plate sequence is not changing approved LP's (62120)	License plate sequence is not changing approved LP's. The system now correctly updates LP disposition codes to Passed Advanced Quality Orders (AQO) for Passed AQO, irrespective of the 'Auto validate priority one lines' setting, ensuring proper inventory availability.
License Plate Sequence Disposition Inconsistent After Priority 1 Pass and Subsequent AQO Failure (62147)	Before this fix the system would ignore the result of the whole advanced quality order if the setting Auto validate priority one lines on Test group header was toggled to "yes". The system now correctly applies disposition code updates to all license plates within a sequence if the Advanced Quality Order fails, even if a Priority 1 test initially passed. Batch disposition master settings are of course respected if disposition codes are set to disallow automatic updates.
The AQO frequency is wrong, when changing item group (62130)	The frequency in which tests are triggered has been optimized / fixed. Now the frequency on both test groups and the individual tests are controlled towards the choice on Advanced quality order creation criteria on the advanced quality association and on the test group lines in the fields "Sequence types" and "frequency". User manual updated with a new section about frequencies which extensively explains the different frequencies, the common settings and how they work together.
Error thrown when Reverse work functionality in Outbound load is triggered (61876)	Error was thrown when Reverse work functionality in Outbound load is triggered. The reservation mechanism in the Quality and Sample Management module has been

Functionality	Description
	corrected to properly handle products with Batch and Serial tracking where Serial is above Location in the reservation hierarchy when reversing work for Loads.

50.3. Known Issues

Number	Name	Description
61250	Disposition code non-nettable on LP level is still being counted as nettable	It is not possible to force nor extend Planning Optimization Add-in to support being able to control stock visibility and availability using License Plate disposition codes. Microsoft recommendation is to use old Master Planning solution.

51. CEPHEO BUILD 10.0.20251007.1

51.1. General

This document describes the features that are either new or changed in the release version mentioned.

Release Information

CEPHEO Quality Sample and Sample Management Version	Release Date
10.0.20251007.1	October 7, 2025

The following Microsoft version was used to build the release

Base	Version	Build Number	Release
Application	10.0.42	10.0.2095.59	What's new or changed in Dynamics 365 Finance 10.0.42 (December 2024) - Finance Dynamics 365 Microsoft Learn
Platform	Platform Update 66	7.0.7452.66	What's new or changed in Platform update 65 for Finance and Operations apps

51.2. Fixed

Functionality	Description
Missing data entities for Test groups members (advanced quality control) (62267)	Additional missing 3 fields from Test groups members was added to EGLAQCIInventTestGroupMemberEntity.
Extension point for EGLQSMEGLAQCIInventQualityOrderLine Extension.pdsCanUpdateAttributeValue (62294)	Extension point for Cepheo Software Module Quality and sample management added.
Automatic transfer of batch attributes (62406)	The automatic transfer of batch attributes has been fixed and improved. For further details, see Quality and Sample Management user guide, section 4.3.16

51.3. Known Issues

Number	Name	Description
61250	Disposition code non-nettable on LP level is still being counted as nettable	It is not possible to force nor extend Planning Optimization Add-in to support being able to control stock visibility and availability using License Plate disposition codes. Microsoft recommendation is to use old Master Planning solution.

